Configuring Objects for Event Logging

The **Audit Settings** page on the **Events** menu provides control over the event logging of most common objects found in the RiskVision application. You can configure operations for the various objects and make RiskVision write the information required. The default enabled operations of different objects are shown in the table below:

Object Type	Enabled Operations	
Assessment, Controls, Custom Charts, Dashboards, Data Feeds, Document Repository, Email Templates, Entity, Exceptions, Filters, Findings, Incidents, Program, Questionnaire, Questionnaire Preferences, Report Templates, Reports, Risk, Risk Profiles, Sub Controls, Effectiveness Tests & Design Tests, System Users, Teams, Tenants, Threats, Tickets, Vulnerabilities, and Workflow	Create, Update, Delete, and Import	
Scheduled Jobs	Start, Update, Create, Finish, Delete, and Run	

The operations that are not enabled are not logged by the RiskVision Server and therefore those events are not available on the **Administration** > **Events** page and for reporting purposes.

To view enabled operations of objects that are logged:

1. In the Administration application, go to Events > Audit Settings. The Audit Settings page is displayed.

2.

Administration	Users	Events			
Audit Events Au	dit Settings	5			About this page
Configure object Le	evel Audit				Save 🔞 Cancel
	•	Configure	Object Audit	Settings	
Object Level Aud	iit >	Assessmen Controls Custom Cha Dashboards Data Feeds Document R Email Templ Entity Exceptions Filters	Dispects: ts rts epository ates	 Import ✓ Update ✓ Create ✓ Delete 	
		Finding Incidents Program Questionnai Preferences Report Temp Reports	re re ilates		

3. In the **Configurable Objects** box, select the object of interest to see the enabled operations on the right-hand side. Select the objects one by one to see the operations for which the events are logged by the RiskVision Server.

To configure objects for event logging:

- 1. In the Administration application, go to Events > Audit Settings. The Audit Settings page is displayed.
- 2. Click Edit at the top-right corner of the page.
- 3. In the **Configurable Objects** box, select the object, and perform the tasks given below:
 - 1. Check the box next to the operation type if you want to log events for the operation.
 - 2. Clear the box next to the operation type if you don't want to log events for the operation.
- 4. Click **Save** after performing the desired changes.

The changes to event logging are applied.