

Configuring a Threshold Range for Calculating Vulnerability Scores


A common threshold range criteria must be established for assessment, finding, and risk objects. When assessments are run, the vulnerability scores are derived according to the scale that has been defined for a range. Before running an assessment, ensure that the threshold range is configured to meet the auditing guidelines and policies of the assessment objectives.

Each configuration range allows the user to adjust the threshold range by specifying the numeric value, unique name, color, and the option to display text or a score.










In order to adjust the configurations, you must have the Tenant Configure permission.

To set up Assessment Configuration:

1. Open the Enterprise Risk Manager.
2. Go to **Configuration > Assessment Configuration**.



The screenshot shows the 'Assessment Configuration' interface. On the left is a blue sidebar with a 'Ranges' section. The main area displays a table with columns: Threshold For, Threshold, Label, Color, and Display. There are three radio buttons for 'Assessment Risk Scale', 'Individual Risk Scale', and 'Program Risk Scale'. The 'Assessment Risk Scale' is selected. The table lists three ranges for each scale, with colors (Green, Orange, Red) and display options (text or N/A).

Threshold For	Threshold	Label	Color	Display
<input checked="" type="radio"/> Assessment Risk Scale	Risk Score < 150	Low	Green	 text
	150 <= Risk Score < 300	Medium	Orange	 text
	300 <= Risk Score	High	Red	 text
<input type="radio"/> Individual Risk Scale	Risk Score < 30	Low	Green	 text
	30 <= Risk Score < 70	Medium	Orange	 text
	70 <= Risk Score	High	Red	 text
<input type="radio"/> Program Risk Scale	Risk Score < 300	Low	Green	 text
	300 <= Risk Score < 600	Medium	Orange	 text
	600 <= Risk Score	High	Red	 N/A

The Assessment Configuration tab.

3. Select **Assessment Risk Scale**, then click **Edit**.

Configure Threshold
✕

Threshold For: Assessment Risk Scale Revert

Threshold		Label	Color	Display
Less than	<input style="width: 40px;" type="text" value="150"/> <input style="width: 25px; height: 25px; border: 1px solid #ccc; border-radius: 3px; text-align: center; margin: 0 5px;" type="button" value="+"/> <input style="width: 25px; height: 25px; border: 1px solid #ccc; border-radius: 3px; text-align: center; margin: 0 5px;" type="button" value="-"/>	<input style="width: 60px;" type="text" value="Low"/>	<input style="width: 80px;" type="text" value="Green"/> 	<input checked="" type="radio"/> Text <input type="radio"/> Score
Between 150 and	<input style="width: 40px;" type="text" value="300"/> <input style="width: 25px; height: 25px; border: 1px solid #ccc; border-radius: 3px; text-align: center; margin: 0 5px;" type="button" value="+"/> <input style="width: 25px; height: 25px; border: 1px solid #ccc; border-radius: 3px; text-align: center; margin: 0 5px;" type="button" value="-"/>	<input style="width: 60px;" type="text" value="Medium"/>	<input style="width: 80px;" type="text" value="Orange"/> 	<input checked="" type="radio"/> Text <input type="radio"/> Score
Greater than	<input style="width: 40px;" type="text" value="300"/>	<input style="width: 60px;" type="text" value="High"/>	<input style="width: 80px;" type="text" value="Red"/> 	<input checked="" type="radio"/> Text <input type="radio"/> Score

The Configure Threshold dialog.

4. Click + or – to add or remove a threshold range. For any assessment configuration, you can add a maximum of five threshold ranges. At a minimum, any configuration range contains two threshold ranges.
5. **Optional:**
 - To modify a range, enter a numerical value in the threshold range field.
 - To change the threshold display name, enter a name in the **Label** field.
 - To assign a color for a threshold, click the **Color** icon, choose the desired color, and click **Close**.
 - Choose the **Text** or **Score** option to display the threshold label or the value for the risk after the assessment is run.
6. Click **Revert** to ignore all the changes or click **OK** to save the configuration.

Similarly, set up **Entity Compliance Configuration**, **Individual Risk Scale**, and **Program Risk Scale**.