

Configuring a Threshold Range for Calculating Vulnerability Scores


A common threshold range criteria must be established for assessment, finding, and risk objects. When assessments are run, the vulnerability scores are derived according to the scale that has been defined for a range. Before running an assessment, ensure that the threshold range is configured to meet the auditing guidelines and policies of the assessment objectives.

Each configuration range allows the user to adjust the threshold range by specifying the numeric value, unique name, color, and the option to display text or a score.














In order to adjust the configurations, you must have the Tenant Configure permission.

To set up Assessment Configuration:

1. Open the Compliance Manager.
2. Go to **Configuration > Assessment Configuration**.



The screenshot shows the 'Assessment Configuration' interface. On the left is a blue sidebar with a 'Ranges' section. The main area displays a table with columns: Threshold For, Threshold, Label, Color, and Display. The table lists configurations for 'Assessment Risk Scale', 'Entity Compliance Configuration', 'Individual Risk Scale', and 'Program Risk Scale', each with three sub-ranges. Each row includes a radio button to select the configuration, a color swatch, and a 'text' or 'N/A' display option.

| Threshold For | Threshold | Label | Color | Display | |
|---|---|-------------|--------|--|--|
| <input type="radio"/> Assessment Risk Scale | Score < 150 | Low | Green |  text | |
| | 150 <= Score < 300 | Medium | Orange |  text | |
| | 300 <= Score | High | Red |  text | |
| <input type="radio"/> Entity Compliance Configuration | Score < 0 | Unknown | Gray |  N/A | |
| | 0 <= Score < 60 | Low | Red |  N/A | |
| | 60 <= Score < 80 | Medium | Orange |  N/A | |
| <input type="radio"/> Individual Risk Scale | 80 <= Score | High | Green |  N/A | |
| | <input type="radio"/> Individual Risk Scale | Score < 30 | Low | Green |  text |
| | 30 <= Score < 70 | Medium | Orange |  text | |
| <input type="radio"/> Program Risk Scale | 70 <= Score | High | Red |  text | |
| | <input type="radio"/> Program Risk Scale | Score < 300 | Low | Green |  text |
| | 300 <= Score < 600 | Medium | Orange |  text | |
| | 600 <= Score | High | Red |  N/A | |

The Assessment Configuration tab.

3. Select **Assessment Risk Scale**, then click **Edit**.

Configure Threshold
✕

Threshold For: Assessment Risk Scale Revert

| Threshold | Label | Color | Display |
|---|--|--|---|
| Less than <input style="width: 50px;" type="text" value="150"/> <input type="button" value="+"/> <input type="button" value="-"/> | <input style="width: 50px;" type="text" value="Low"/> | <input style="width: 50px;" type="text" value="Green"/> | <input checked="" type="radio"/> Text <input type="radio"/> Score |
| Between 150 and <input style="width: 50px;" type="text" value="300"/> <input type="button" value="+"/> <input type="button" value="-"/> | <input style="width: 50px;" type="text" value="Medium"/> | <input style="width: 50px;" type="text" value="Orange"/> | <input checked="" type="radio"/> Text <input type="radio"/> Score |
| Greater than <input style="width: 50px;" type="text" value="300"/> | <input style="width: 50px;" type="text" value="High"/> | <input style="width: 50px;" type="text" value="Red"/> | <input checked="" type="radio"/> Text <input type="radio"/> Score |

The Configure Threshold dialog.

4. Click + or – to add or remove a threshold range. For any assessment configuration, you can add a maximum of five threshold ranges. At a minimum, any configuration range contains two threshold ranges.
5. **Optional:**
 - To modify a range, enter a numerical value in the threshold range field.
 - To change the threshold display name, enter a name in the **Label** field.
 - To assign a color for a threshold, click the **Color** icon, choose the desired color, and click **Close**.
 - Choose the **Text** or **Score** option to display the threshold label or the value for the risk after the assessment is run.
6. Click **Revert** to ignore all the changes or click **OK** to save the configuration.

Similarly, set up **Entity Compliance Configuration**, **Individual Risk Scale**, and **Program Risk Scale**.