



Configuring Entity Compliance and Criticality Ranges

The Range option controls the numeric score for the low, medium, and high or VL (very low), L (low), M (medium), H (high), and VH (very high) selections a user can make on various RiskVision pages as well as the color and ranges that display in graphs and charts on dashboard pages and reports:

- **Compliance range:** Controls the numeric values for displaying overall compliance levels, such as on the Assessment Details > Control Results > Compliance Summary pane.



- **Criticality values:** Controls numeric values for the choices on Entity Details > Classification > Security Requirement. The Business criticality is an average of the confidentiality, integrity, and availability security requirement settings. It displays on the Assessment Details page and in reports.



To modify a range:

1. Go to **Configuration > Entity Configuration**.

2. Click **Ranges**.

The screenshot shows a dialog box titled "Configure Threshold" with a close button (X) in the top right corner. Below the title bar, the text "Threshold For: Entity Criticality Configuration" is displayed on the left, and a "Revert" button is on the right. The main area contains a table with four rows, each representing a different threshold range. Each row has columns for "Threshold", "Label", "Color", and "Display". The "Threshold" column includes a text input field and buttons for "+" and "-". The "Color" column shows a color selection box with a preview. The "Display" column has radio buttons for "Text" and "Score". At the bottom right of the dialog are "OK" and "Cancel" buttons.

| Threshold | Label | Color | Display |
|-----------------|---------|-------|---|
| Less than 0 | Unknown | Gray | <input type="radio"/> Text <input checked="" type="radio"/> Score |
| Between 0 and 5 | Low | Green | <input checked="" type="radio"/> Text <input type="radio"/> Score |
| Between 5 and 7 | Mediumu | Gold | <input checked="" type="radio"/> Text <input type="radio"/> Score |
| Greater than 7 | High | Red | <input checked="" type="radio"/> Text <input type="radio"/> Score |

3. Choose **Entity Criticality Configuration** and click **Edit**.
4. If you want to increase the Threshold range, click + (plus symbol).
5. Click -(minus symbol) to decrease the Threshold range. The color will change based on the selected Threshold range.
6. Click **OK**.