

Entity Import Template

The table below lists the attributes available for importing entities and entity collections:

Attribute	Description
*caption	Enter the name of an entity.
description	Any additional information that helps understand the purpose of creating an entity.
*name	Specify the name of an entity.
stage	Enter '1' to import an entity as managed.
*assetType	Specify the type of an entity.
assetSubtype	The entity subtype.
assetTag	Specify a label for an entity.
serialNumber	Specify the serial number of an entity. Not all entity types contain the Serial Number attribute.
model	Specify the model number of an entity. Not all entity types contain the Model attribute.
manufacturer	Specify the manufacturer of an entity. Not all entity types contain the Manufacturer attribute.
version	Specify the version number of an entity. Not all entity types contain the Version attribute.
organization	Specify the name of an organization that owns an entity.
division	Specify the name of a division that owns an entity.
subDivision	Specify the name of a sub division if that particular division is composed of separate parts.
classification.integrityImpact	Specify the impact affecting the integrity.
assetInformation.dataIntegrityCost	Specify the cost involved in maintaining the data integrity.
ownerships.1.ownershipType.name	Specify the owner's name for the ownership type.
ownerships.1.ownerId	Specify the owner ID for an entity owner.
ownerships.1.teamownerId	Specify the team owner ID for an entity owner.
ownerships.2.ownershipType.name	Specify the owner's name for the ownership type.
ownerships.2.ownerId	Specify the owner ID for an entity owner.
ownerships.2.teamownerId	Specify the team owner ID for an entity owner.
ownerships.3.ownershipType.name	Specify the owner's name for the ownership type.
ownerships.3.ownerId	Specify the owner ID for an entity owner.
ownerships.3.teamownerId	Specify the team owner ID for an entity owner.
ownerships.4.ownershipType.name	Specify the owner's name for the ownership type.
ownerships.4.ownerId	Specify the owner ID for an entity owner.
ownerships.4.teamownerId	Specify the team owner ID for an entity owner.
addressLinks.1.addressType.name	Specify the name of the address type, such as permanent address and billing address, to help indicate the preferred mode of communication.
address.Links.1.address.name	Specify the name of the address to help locate an entity.
addressLinks.1.address.country	Specify the name of the country.
addressLinks.2.addressType.name	Specify the name of the address type, such as permanent address and billing address, to help indicate the preferred mode of communication.
address.Links.2.address.name	Specify the name of the address to help locate an entity.
addressLinks.2.address.country	Specify the name of the country.
tags.1.name	Enter the name of the tag.
tags.1.category	The name of the category for grouping common entities.
tags.1.description	Any additional information that will help demonstrate the purpose of creating a tag.
hardware.1.cpe.uri	Specify the uri of the cpe.
hardware.1.cpe.title	Title of the cpe.
hardware.1.cpe.description	Description of the cpe.
hardware.1.cpe.update	Specify the hardware revision number.
hardware.1.cpe.edition	Specify the edition of CPE.
hardware.1.cpe.language	Enter the language.
hardware.1.cpe.product	Enter the product name.

Attribute	Description
hardware.1.cpe.version	Version of the CPE.
hardware.1.cpe.vendor	Vendor name of the CPE.
hierarchies.1.hierarchyType	Specify the organization hierarchy type.
hierarchies.1.description	Specify the purpose for creating an organization hierarchy.
hierarchies.1.level1	Specify the first level of the organization hierarchy.
hierarchies.1.level2	The second level of the organization hierarchy.
hierarchies.1.level3	The third level of the organization hierarchy.
customAttributes.boolean1	The custom boolean attribute to be added to the entity.
vendorServices.1.name	The name of the vendor service.
vendorServices.1.defaultFlag	Enter "1" to import vendor service as Default.
vendorServices.1.serviceType	Specify the type of the vendor service.
vendorServices.1.ownerships.1.ownershipType.name	Specify the owner for the ownership type of a vendor service.
vendorServices.1.ownerships.1.ownerId	The owner ID of the vendor service owner.



1. Organization hierarchy must be available in the Vendor Risk Manager prior to importing of Vendor Contact.
2. Enter '1' in the vendorServices.1.stage attribute field to import as managed vendor services.