



# Configuring Entity Compliance and Criticality Ranges

The Range option controls the numeric score for the low, medium, and high or VL (very low), L (low), M (medium), H (high), and VH (very high) selections a user can make on various RiskVision pages as well as the color and ranges that display in graphs and charts on dashboard pages and reports:

- **Compliance range:** Controls the numeric values for displaying overall compliance levels, such as on the Assessment Details > Control Results > Compliance Summary pane.




- **Criticality values:** Controls numeric values for the choices on Entity Details > Classification > Security Requirement. The Business criticality is an average of the confidentiality, integrity, and availability security requirement settings. It displays on the Assessment Details page and in reports.



To modify a range:

1. Go to **Configuration > Entity Configuration**.

2. Click **Ranges**.



The image shows a 'Configure Threshold' dialog box with a blue header and a red close button. The title bar reads 'Configure Threshold'. Below the header, the text 'Threshold For: Entity Criticality Configuration' is displayed on the left, and a 'Revert' link is on the right. The main area contains a table with four rows, each representing a different threshold range. Each row has columns for 'Threshold', 'Label', 'Color', and 'Display'. The 'Threshold' column includes a text input field and '+' or '-' buttons. The 'Color' column shows a color selection box with a preview. The 'Display' column has radio buttons for 'Text' and 'Score'. At the bottom right, there are 'OK' and 'Cancel' buttons.

Threshold	Label	Color	Display
Less than 0	Unknown	Gray	<input type="radio"/> Text <input checked="" type="radio"/> Score
Between 0 and 5	Low	Green	<input checked="" type="radio"/> Text <input type="radio"/> Score
Between 5 and 7	Mediumu	Gold	<input checked="" type="radio"/> Text <input type="radio"/> Score
Greater than 7	High	Red	<input checked="" type="radio"/> Text <input type="radio"/> Score

3. Choose **Entity Criticality Configuration** and click **Edit**.
4. If you want to increase the Threshold range, click + (plus symbol).
5. Click - (minus symbol) to decrease the Threshold range. The color will change based on the selected Threshold range.
6. Click **OK**.