

Configure a Threshold Range for Calculating Risk Scores


A common threshold range criteria must be established for assessment, finding, and risk objects. When assessments are run, risk scores are derived according to the scale that has been defined for a range. Before running an assessment, ensure that the threshold range is configured to meet the auditing guidelines and policies of the assessment objectives.

Each configuration range allows the user to adjust the threshold range by specifying the numeric value, unique name, color, and the option to display text or a numeric score.














In order to adjust the configurations, you must have the Tenant Configure permission.

To set up Assessment Configuration:

1. Open the Vendor Risk Manager.
2. Go to **Configuration > Assessment Configuration**.



The screenshot shows the 'Assessment Configuration' interface. On the left is a blue sidebar with the 'Ranges' tab selected. The main area displays a table with columns: Threshold For, Threshold, Label, Color, and Display. The table lists configurations for 'Assessment Risk Scale', 'Entity Compliance Configuration', 'Individual Risk Scale', and 'Program Risk Scale'. Each configuration has three rows representing different score ranges with corresponding labels and colors.

Threshold For	Threshold	Label	Color	Display
<input type="radio"/> Assessment Risk Scale	Score < 150	Low	Green	 text
	150 <= Score < 300	Medium	Orange	 text
	300 <= Score	High	Red	 text
<input type="radio"/> Entity Compliance Configuration	Score < 0	Unknown	Gray	 N/A
	0 <= Score < 60	Low	Red	 N/A
	60 <= Score < 80	Medium	Orange	 N/A
<input type="radio"/> Individual Risk Scale	80 <= Score	High	Green	 N/A
	Score < 30	Low	Green	 text
	30 <= Score < 70	Medium	Orange	 text
<input type="radio"/> Program Risk Scale	70 <= Score	High	Red	 text
	Score < 300	Low	Green	 text
	300 <= Score < 600	Medium	Orange	 text
	600 <= Score	High	Red	 N/A

The Assessment Configuration tab.

3. Click **Assessment Risk Scale**, then click **Edit**.

Configure Threshold ✕

Threshold For: Assessment Risk Scale Revert

Threshold		Label	Color	Display
Less than	<input style="width: 40px;" type="text" value="150"/> <input type="button" value="+"/> <input type="button" value="-"/>	<input style="width: 50px;" type="text" value="Low"/>	<input style="width: 80px;" type="text" value="Green"/> 	<input checked="" type="radio"/> Text <input type="radio"/> Score
Between 150 and	<input style="width: 40px;" type="text" value="300"/> <input type="button" value="+"/> <input type="button" value="-"/>	<input style="width: 50px;" type="text" value="Medium"/>	<input style="width: 80px;" type="text" value="Orange"/> 	<input checked="" type="radio"/> Text <input type="radio"/> Score
Greater than	<input style="width: 40px;" type="text" value="300"/>	<input style="width: 50px;" type="text" value="High"/>	<input style="width: 80px;" type="text" value="Red"/> 	<input checked="" type="radio"/> Text <input type="radio"/> Score

The Configure Threshold dialog.

4. Click + or - to add or remove a threshold range. For any assessment configuration, you can add a minimum of two and a maximum of five threshold ranges.
5. **Optional:** Perform any of the following actions:
 - To modify a range, enter a numerical value in the threshold range field.
 - To change the threshold display name, enter a name in the **Label** field.
 - To assign a color for a threshold, click the **Color** icon, choose a desired color, and then click **Close**.
 - Choose the **Text** or **Score** option to display the threshold label or the value for the risk after the assessment is run.
6. Click **Revert** to ignore all changes or click **OK** to save.

Similarly, set up **Entity Compliance Configuration**, **Individual Risk Scale**, and **Program Risk Scale**.

