

Batch Edit Compensating Controls

Users with the Entity View, Threats and Vulnerabilities View, and Vulnerability Compensating Control Update permissions can use the **Batch Edit VCC** action to edit the status of multiple vulnerability compensating controls attached to a single entity. Alternatively, users with the Entity View, Entity Manage, Threats and Vulnerability View, and Vulnerability Compensating Controls Update permissions can edit vulnerability compensating controls attached to multiple entities.



Batch editing vulnerability compensating controls across multiple entities can only be done for compensating controls that the entities have in common.

To batch edit vulnerability compensating controls on a single entity:

1. In the Threat & Vulnerability Manager application, navigate to **Entities > Entities**.

Name	Type	Subtype	Criticality	Owner	Description
All-Low	Computer	N/A	Green		N/A
E11	Computer	N/A	Green		N/A
E1234	Computer	N/A	Green		D

The Entities list.

2. Click the entity that contains the vulnerability compensating control or controls that you wish to edit.

Information

Name	E11	Installation date	N/A
Description	N/A	Last maintenance date	N/A
Entity type	Computer	Maintenance reference	N/A
Entity subtype	N/A	Warranty expiration date	N/A
Manufacturer	N/A	Warranty reference	N/A
Serial number	N/A		
Product name	N/A		

Entity Management


Tracked since	2020-07-10
Status	Managed
Data source(s)	Manual entry
Author	
Created on	2020-07-10
Discovery source	N/A
Custom String 10	N/A
Custom String 9	N/A

Organization Hierarchy

Organization Root	Path	Description
No assigned Hierarchies found.		


The Entity Details page.

3. Navigate to the **Comp Controls** tab under the **Vulnerabilities** tab.




The Comp Controls tab.

4. Select each compensating control to be edited and select **Batch Edit VCC** from the **More Actions...** select list.



The Editing Multiple Vulnerability Compensating Controls page.

5. Click **Edit**.
6. Select the status the compensating controls should be set to in the **Status** select list.



The Status select list.

7. Click **Save**.

To batch edit vulnerability compensating controls across multiple entities:

1. In the Threat & Vulnerability Manager application, navigate to **Entities > Entities**.

Name	Type	Subtype	Criticality	Owner	Description
All-Low	Computer	N/A	100%		N/A
E11	Computer	N/A	50%		N/A
E1234	Computer	N/A	50%		D

The Entities list.

2. Select each entity that contains the vulnerability compensating control or controls that you wish to edit and click **Batch Edit Entities**.

The Editing Multiple Entities page.

3. Navigate to the **Comp Controls** tab.

Editing Multiple Entities: 2 Entities

Vulnerability Compensating Controls

1-3 of 3

Filter by

<input type="checkbox"/>	Title	Description	Category	Status	Last Updated
<input type="checkbox"/>	Web content filtering	N/A	Network Compensating Controls	Implemented	2020-07-15
<input type="checkbox"/>	Network intrusion prevention	N/A	Network Compensating Controls	Implemented	2020-07-14
<input type="checkbox"/>	Network behavioral analysis	N/A	Network Compensating Controls	Implemented	2020-07-14

The Comp Controls tab.

- Select each compensating control to be edited and select **Batch Edit VCC** from the **More Actions...** select list.

Editing Multiple AssetToVulnCC: 8 EntityToVCCs

General

Vulnerability Compensating Control Details

Vulnerability Compensating Control
Status Implemented

The Edit Multiple Vulnerability Compensating Controls page.

- Click **Edit**.
- Select the status the compensating controls should be set to in the **Status** select list.

Editing Multiple AssetToVulnCC: 8 EntityToVCCs

General

Vulnerability Compensating Control Details

Vulnerability Compensating Control
Status

Select a status

- Implemented
- Pending

The Status select list.

- Click **Save**.