


## Hardware

Installed hardware can be found on the Computer, Network Device, and Mobile Device entity types. Typically, this data is imported from scanners, but there may be times when you may want to manually update the data.

### To view an entity's hardware grid:

1. Open the **Entity Details** page.
2. Click **+** to expand the **System Details** tab, then click **Hardware**.



The screenshot shows a web application interface for a computer entity named 'High17'. On the left is a blue sidebar with a menu containing: General, Assessments, Vulnerabilities, Threats, System Details (expanded), Network, Ports, Services, Applications, Hardware (selected), Patches, Network Shares, User Accounts, Membership, Data Feeds, and Exceptions. The main content area is titled 'Installed hardware' and shows a table with 3 records. Above the table are buttons for 'New', 'Add', 'Delete', and 'More Actions...'. To the right of the table are 'Filter by' and 'Refresh' buttons. The table has columns for Vendor, Product, Version, and CPE URI.

Vendor	Product	Version	CPE URI
3com	3crwe454g72	1.0.2	cpe:2.3:h:3com:3crwe454g72:1.0.2:*****
3com	3crwe454g72	-	cpe:2.3:h:3com:3crwe454g72:--:*****
360	f5c_router	-	cpe:2.3:h:360:f5c_router:--:*****

*The Hardware grid.*

### To add a new hardware record:

1. Open the entity's hardware grid.
2. Click **New**.
3. Fill in the following fields in the **Hardware** dialogue:
  - a. **Full Name:** Enter the name of the hardware. This must be a relevant name.
  - b. **Description:** Enter any information that describes the hardware.
  - c. **Vendor:** Enter the name of the organization that offers the hardware.
  - d. **Product.** Enter the product name. This is a short name for the hardware.
  - e. **Version.** Enter the version number of the hardware. This helps you notice the differences between the new version and the old version.
  - f. **Update.** Enter the hardware revision number, if available. You can derive this field if your application includes the most recent fix.
  - g. **Edition.** Enter the edition, such as standard, professional, or enterprise, if applicable.
  - h. **Language.** Enter the language if the hardware is procured for non-native English users.
  - i. **Software Edition:** If the hardware contains any software, enter the edition of that software.
  - j. **Target Software:** Enter the target software of the hardware, if applicable.
  - k. **Target Hardware:** Enter the target hardware of the hardware, if applicable.
  - l. **Other:** Enter any other details about the hardware.
  - m. **Validated:** Select **Yes** if the hardware has been validated.

- n. **Version Name:** The name of the hardware's version, if applicable.
- o. **Serial Number:** The serial number of the hardware, if any.

**Hardware** [Close]

Full Name\* [Text Box]

Description [Text Box]

Vendor\* [Text Box]

Product\* [Text Box]

Version \* [Text Box]

Update \* [Text Box]

Edition \* [Text Box]

Language \* [Text Box]

Software Edition \* [Text Box]

Target Software \* [Text Box]

Target Hardware \* [Text Box]

Other \* [Text Box]

Validated  Yes  No

Version name [Text Box]

Serial number [Text Box]

[OK] [Cancel]

*The Hardware dialogue.*

- 4. Click **OK** to add the hardware.

## To add an existing hardware record:

- 1. Open the entity's hardware grid.
- 2. Click **Add**.

**Choose Hardware**
✕

Title

Vendor

Product

Version

**Search**

**Or Just Enter Keyword**

Keyword

Show Technologies With Deployed Entities Only

i Found more than 200 matches. Showing first 200.

**Known Hardware**

360 F5C Router cpe:2.3:h:360:f5c\_router:-:\*\*\*\*\*

360 P0 Router cpe:2.3:h:360:p0\_router:-:\*\*\*\*\*

3Com 3Com OfficeConnect Wireless11g Access Point cpe:2.3:h:3com:3crwe454g72:-:\*\*\*\*\*

3Com 3Com OfficeConnect Wireless11g Access Point 3CRWE454G72 1.0.2 cpe:2.3:h:3com:3crwe454g72

3Com 3Com OfficeConnect Wireless11g Access Point 3CRWE454G72 1.0.2.11 cpe:2.3:h:3com:3crwe454g

3Com 3Com OfficeConnect Wireless11g Access Point 3CRWE454G72 1.0.3.5 cpe:2.3:h:3com:3crwe454g7

↓ ↑

**Selected Hardware**

OK
Cancel

*The Choose Hardware dialogue.*

3. Search for the hardware using the following fields to narrow the search results:
  - **Title.** Enter the hardware's title.
  - **Vendor.** Enter the vendor's name.
  - **Product:** Enter the product name.
  - **Version:** Enter the application's version number.
4. **Optional:** Enter a keyword in the **Keyword** field.
5. Click **Search**.
6. The results are returned and displayed in the **Known Hardware** box. If the search returns too many hardware records, use the scroll-bar to find the desired one.
7. After you locate the hardware, select it in the **Known Hardware** box, and click the arrow pointing downward to move the application into the **Selected Hardware** box. Multiple hardware records can be added at once.
8. Click **OK** to add the selected hardware records.

### To delete a hardware record:

1. Open the entity's hardware grid.
2. Select the box in the corresponding hardware row, then click **Delete**.

### To edit a hardware record:

1. Open the entity's hardware grid.

2. Select the box in the corresponding hardware row.
3. Click **Edit** in the **More Actions** dropdown list to display the **Hardware** dialogue.
4. Edit the fields as desired.
5. Click **OK** to confirm the changes.